# LiveCode 4.6.4 Release Notes

# **Table of Contents**

Overview	4
Known issues	4
Platform support	4
Windows	4
Linux	4
Mac	5
Proposed changes	5
Setup	6
Installation	6
Uninstallation	6
Reporting installer issues	6
Activation	
Multi-user and network install support (4.5.3)	7
Command-line installation	7
Command-line activation	8
Engine Changes	. 10
MySQL driver updates (4.6.4)	. 10
Shared group and background updates (4.6.4)	. 10
sharedBehavior property	
sharedGroupNames and sharedGroupIds properties	.10
backgroundBehavior property	.11
place command	11
remove command	
Message handling speed improvements (4.6.4)	.11
networkInterfaces property (4.6.3)	. 12
defaultNetworkInterface property (4.6.3)	.12
Mac - revBrowser userAgent property (4.6.2)	.12
Print to PDF document outline support (4.6 – improved 4.6.1)	. 12
Mac – revCapture video capture library (4.6.1 – experimental )	.13
Session management	. 13
Input configuration	.13
Querying available inputs	.14
Configuring the audio input	. 14
Configuring the video input	. 14
Compression configuration.	
Querying available codecs	.14
Configuring the audio codec	. 15
Configuring the video codec	. 15
Preview management.	. 15
Configuring the video preview image	. 15
Configuring the audio preview volume	
Previewing a session	. 16
Record management	16

Configuring the output file	16
Configuring the maximum frame size	16
Configuring the maximum frame rate	16
Starting recording	17
Stopping recording	
Object snapshot with effects (4.6)	
Print to PDF link improvements (4.6)	
Field 'plain text' properties (4.6)	
Out-of-bounds group scrolling (4.6)	
Cryptographic-quality random data (4.6)	
SHA-1 digest support (4.6)	
Public key encryption support (4.6)	
Generating key pairs	
Command variants	
Encrypting longer messages	
Mac – window modification indicator (4.6)	
XML text node access (4.6 – experimental)	
Ordered and unordered lists (4.6 – experimental)	
Properties	
htmlText format	
rtfText format	
plainText format	
Persistence	
XML Namespace support (4.5.1)	
Runtime execution stack configuration (4.5.1 – experimental)	
revBrowser windowId property (4.5.1 – experimental)	
Non-blocking DNS resolution (4.5)	
Improved cursor support (4.5)	
Improved image export (4.5)	26
BMP Export	26
Palette reduction	26
Raw data export (experimental)	
Color profile support (4.5)	27
Print to pdf support (4.5)	27
Print loop integration	28
Options	28
Hyperlink support	
Runtime dependency.	28
Slave process improvements (4.5)	29
Videograbber improvements (4.5)	
Elevated process support (4.5 – experimental)	
Status icon support (4.5 – experimental)	
Listing sub-keys in the registry (4.5 – experimental)	
HTTPS – automatic root certificate discovery (4.5 – experimental)	
Mac – dock icon support (4.5 – experimental)	
Choosing an image	
Configuring the dock icon menu	
Maintenance	
Noteworthy changes	32

Specific bug fixes (4.6.4)	35
Specific bug fixes (4.6.3)	
Specific bug fixes (4.6.2)	
Specific bug fixes (4.6.1)	
Specific bug fixes (4.6)	36
IDE Changes	38
Getting folder locations within the IDE	38
Update checker	
Affiliate registration	38
Database query builder	
Android Support (4.6.1)	38
iOS Support (4.5.2)	39
Access to resources folder (4.5.2)	39
Standalone builder	40
Windows – UAC Manifest	40
Web	40
Android (4.6.1)	40
iOS (4.5.2)	40
Datagrid	40
Maintenance	41
Noteworthy changes	41
Specific bug fixes (4.6.4)	41
Specific bug fixes (4.6.3)	41
Specific bug fixes (4.6.2)	42
Specific bug fixes (4.6.1)	
Specific bug fixes (4.6)	
Resource and Documentation Changes	
User Guide	
Dictionary	43
Mobile Examples	
Previous Release Notes	44
Revisions	44

#### **Overview**

LiveCode 4.6.4 is an update to 4.6 containing bug fixes, minor enhancements.

This document describes all the changes that have been made – including bug fixes and new syntax.

For information about improvements made to the iOS port of the engine, please see the iOS Release Notes PDF.

For information about improvements made to the Android port of the engine, please see the Android Release Notes PDF.

At the time of writing, this information has yet to been integrated into the dictionary or User's Guide.

#### **Known issues**

• The installer will currently fail if you run it from a network share on Windows. Please copy the installer to a local disk before launching on this platform.

## **Platform support**

The engine supports a variety of operating systems and versions. This section describes the platforms that we ensure the engine runs on without issue (although in some cases with reduced functionality).

#### Windows

The engine supports the following Windows OSes:

- Windows 2000 SP4
- Windows XP SP2 and above
- Windows Server 2003
- Windows Vista SP1 and above (both 32-bit and 64-bit)
- Windows 7 (both 32-bit and 64-bit)
- Windows Server 2008

*Note:* On 64-bit platforms the engine still runs as a 32-bit application through the WoW layer.

#### Linux

The linux engine requires the following:

- 32-bit installation, or a 64-bit linux distribution that has a 32-bit compatibility layer
- 2.4.x or later kernel
- X11R5 capable Xserver running locally on a 24-bit display
- glibc 2.3.2 or later

- gtk/gdk/glib (optional required for native theme support)
- pango/xft (optional required for pdf printing, anti-aliased text and unicode font support)
- lcms (optional required for color profile support in JPEGs and PNGs)
- gksu (optional required for elevate process support)

**Note:** The optional requirements (except for gksu and lcms) are also required by Firefox and Chrome, so if your linux distribution runs one of those, it will run the engine.

*Note:* If the optional requirements are not present then the engine will still run but the specified features will be disabled.

**Note:** LiveCode and standalones it builds may work on remote Xservers and in other bit-depths, however this mode of operation is not currently supported.

#### Mac

The Mac engine supports:

- 10.4.11 (Tiger) on Intel and PowerPC
- 10.5.8 and later (Leopard) on Intel and PowerPC
- 10.6.x (Snow Leopard) on Intel
- 10.7.x (Lion) on Intel

**Note:** The engine runs as a 32-bit application regardless of the capabilities of the underlying processor.

## **Proposed changes**

The following changes are likely to occur in the next or subsequent non-maintenance release:

• The engine (both IDE and standalone) will require gtk, gdk, glib, pango and xft on Linux

## Setup

#### Installation

The structure of the IDE install has changed significantly in this release.

Each distinct version has its own complete folder – multiple versions will no longer install side-by-side: on Windows (and Linux), each distinct version will gain its own start menu (application menu) entry; on Mac, each distinct version will have its own app bundle.

The default location for the install on the different platforms when installing for 'all users' are:

- Windows: <x86 program files folder>/RunRev/ LiveCode 4.6.4
- Linux: /opt/runrev/livecode-4.6.4-
- Mac: /Applications/ LiveCode 4.6.4.app

The default location for the install on the different platforms when installing for 'this user' are:

- Windows: <user roaming app data folder>/RunRev/Components/LiveCode 4.6.4
- Linux: ~/.runrev/components/livecode-4.6.4
- Mac: ~/Applications/ LiveCode 4.6.4.app

**Note:** If your linux distribution does not have the necessary support for authentication (gksu) then the installer will run without admin privileges so you will have to manually run it from an admin account to install into a privileged location.

#### Uninstallation

On Windows, the installer hooks into the standard Windows uninstall mechanism. This is accessible from the appropriate pane in the control panel.

On Mac, simply drag the app bundle to the Trash.

On Linux, the situation is currently less than ideal:

- open a terminal
- *cd* to the folder containing your rev install. e.g.

```
cd /opt/runrev/livecode-4.6.4
```

• execute the .setup.x86 file. i.e.

follow the on-screen instructions.

## Reporting installer issues

If you find that the installer fails to work for you then please file a bug report in the RQCC or email <u>support@runrev.com</u> so we can look into the problem.

In the case of failed install it is vitally important that you include the following information:

- Your platform and operating system version
- The location of your home/user folder
- The type of user account you are using (guest, restricted, admin etc.)
- The installer log file located as follows:
  - Windows 2000/XP: <documents and settings folder>/<user>/Local Settings/
  - Windows Vista/7: <users folder>/<user>/AppData/Local/RunRev/Logs
  - Linux: <home>/.runrev/logs
  - Mac: <home>/Library/Application Support/Logs/RunRev

#### Activation

The license system has been replaced in this release.

The new system ties your product licenses to a customer account system, meaning that you no longer have to worry about finding a license key after installing a new copy of LiveCode. Instead, you simply have to enter your email address and password that has been registered with our customer account system and your license key will be retrieved automatically.

Alternatively it is possible to activate the product via the use of a specially encrypted license file. These will be available for download from the customer center after logging into your account. This method will allow the product to be installed on machines that do not have access to the internet.

## Multi-user and network install support (4.5.3)

In order to better support institutions needing to both deploy the IDE to many machines and to license them for all users on a given machine, a number of facilities have been added which are accessible by using the command-line.

**Note:** These features are intended for use by IT administrators for the purposes of deploying LiveCode in multi-user situations. They are not supported for general use.

#### Command-line installation

It is now possible to invoke the installer from the command-line on both Mac and Windows. When invoked in this fashion, no GUI will be displayed, configuration being supplied by arguments passed to the installer.

On both platforms, the command is of the following form:

<exe> install noui options

Here *options* is optional and consists of one or more of the following:

-allusers Install the IDE for all users. If not specified, the install will be done for

the current user only.

-desktopshortcut Place a shortcut on the Desktop (Windows-only)
-startmenu Place shortcuts in the Start Menu (Windows-only)

-location location The location to install into. If not specified, the location defaults to those

described in the Layout section above.

-log *logfile* A file to place a log of all actions in. If not specified, no log is generated. Note that the command-line variant of the installer does not do any authentication. Thus, if you wish to install to an admin-only location you will need to be running as administrator before executing the command.

As the installer is actually a GUI application, it needs to be run slightly differently from other command-line programs.

In what follows <installerexe> should be replaced with the path of the installer executable or app (inside the DMG) that has been downloaded.

On Windows, you need to do:

start /wait <installerexe> install noui options

On Mac, you need to do:

"<installerexe>/Contents/MacOS/installer" install noui options

On both platforms, the result of the installation will be written to the console.

#### Command-line activation

In a similar vein to installation, it is now possible to activate an installation of LiveCode for allusers of that machine by using the command-line. When invoked in this fashion, no GUI will be displayed, activation being controlled by any arguments passed.

On both platforms, the command is of the form:

```
<exe> activate -file license -passphrase phrase
```

This command will load the manual activation file from *license*, decrypt it using the given *passphrase* and then install a license file for all users of the computer. Manual activation files can be downloaded from the 'My Products' section of the RunRev customer accounts area.

This action can be undone using the following command:

```
<exe> deactivate
```

Again, as the LiveCode executable is actually a GUI application it needs to be run slightly differently from other command-line programs.

In what follows ivecodeexe> should be replaced with the path to the installed LiveCode executable or app that has been previously installed.

On Windows, you need to do:

```
start /wait livecodeexe> activate -file license -passphrase phrase start /wait livecodeexe> deactivate
```

On Mac, you need to do:

"clivecodeexe>/Contents/MacOS/LiveCode" activate -file *license* -passphrase *phrase* 

"vecodeexe>/Contents/MacOS/LiveCode" deactivate

On both platforms, the result of the activation will be written to the console.

## **Engine Changes**

### MySQL driver updates (4.6.4)

The MySQL driver has been updated such that the revOpenDatabase function now takes three extra optional parameters.

**revOpenDatabase**(databaseType, host[:port], databaseName, [userName], [password], [useSSL], [socket], [timeout], [autoReconnect])

The additional parameters are as follows:

- socket: The socket or named pipe the driver should use to connect with. If empty, the default for the host will be used.
- timeout: The database read/write timeout in whole seconds. Defaults to 20 seconds if empty or not a positive integer.
- autoReconnect: If the driver should attempt to automatically reconnect to the database on the next interaction after connection has been lost.

## Shared group and background updates (4.6.4)

The concept of the shared group has been re-introduced (removed by way of a bug fix in 4.6). Previously, any group that was placed on multiple card was treated as a background and was therefore placed behind the card in the message path. This has now been updated, allowing for groups placed not to behave as backgrounds – shared groups.

## sharedBehavior property

To accommodate this, a new property the sharedBehavior has been added.

set the sharedBehavior of group "my group" to true

When the **sharedBehavior** property of a group is true, the group will behave as a shared group. A shared group behaves identically to a normal group except that it is not owned by any one card. This means that if a shared group is present on only one card and that card is deleted, the shared group will not be deleted. Instead, the group will become 'unplaced', allowing it to placed onto other cards in the future. The group can still be explicitly deleted using the 'delete' command, in which case it will be removed from all cards on which it is placed.

Only top-level groups may be shared groups; an attempt to set the **sharedBehavior** of a nested group to true will throw an error.

An attempt to set the **sharedBehavior** of a shared group to false when it is placed on more than one card, or not placed on any cards will through an error. i.e. To change a shared group to a normal group, the group must be present on one card.

## sharedGroupNames and sharedGroupIds properties

Two further properties the sharedGroupNamess and the sharedGroupIds have been added.

get the sharedGroupIds of stack "my stack"

get the sharedGroupIds of card "my card"
get the sharedGroupNames of stack "my stack"
get the sharedGroupNames of card "my card"

These properties behave in a similar fashion to the **backgroundGroupIds** / **groupIds** / **backgroundGroupNames** / **groupNames** properties that already exist.

The **sharedGroupIds** of a stack will return a list of ids of all groups owned by the stack which have **sharedBehavior** set to true regardless of which cards they may be placed on. The **sharedGroupIds** of a card will return a list of ids of all groups which are placed onto the card which have **sharedBehavior** set to true.

The **sharedGroupNames** of a stack will return a list of short names of all groups owned by the stack which have **sharedBehavior** set to true regardless of which cards they may be placed on. The **sharedGroupNames** of a card will return a list of short names of all groups which are placed onto the card which have **sharedBehavior** set to true.

## backgroundBehavior property

As a result of the shared group updates, **the backgroundBehavior** property has been updated. Previously, groups placed on more than one card were always considered backgrounds and would have their **backgroundBehvior** set to true. This is no longer the case.

Backgrounds groups are now also shared groups. This means that when the **backgroundBehavior** is set to true, the **sharedBehavior** will also be set to true (if it is not already).

## place command

As a result of the shared group updates, the **place** command has been updated.

If the group did not previously have the **sharedBehavior** property set to true, placing a group will set its **backgroundBehavior** property to true. This is legacy behavior and will be removed in version 5.0. Scripts that rely on **place** setting **backgroundBehavior** to true for new groups should be updated to explicitly do so after the **place** command.

#### remove command

As a result of the shared group updates, the **remove** command has been updated.

Only top-level groups may be removed from cards; an attempt to remove a nested group from a card will throw an error.

Removing a group from a card will automatically set the **sharedBehavior** property of the group to true. (The only case this changes that property is if the group is only present on a single card, in which case it becomes unplaced and therefore, by implication, shared).

## **Message handling speed improvements (4.6.4)**

The first steps required for the updating the graphics architecture have been carried out. As a result, the time taken for a message to pass (un-handled) through the message path in the IDE has been reduced by about 2/3rds.

## networkInterfaces property (4.6.3)

On all desktop and server platforms, you can now get a list of the network interfaces of the current machine. This is a return-delimited list of IPv4 addresses that can be accesses by the read only property **the networkInterfaces**.

#### get the networkInterfaces

The IP addresses returned will be in the form required by the defaultNetworkInterface property.

## defaultNetworkInterface property (4.6.3)

On all desktop and server platforms, you can now get and set **the defaultNetworkInterface** property. **The defaultNetworkInterface** determines which network interface should be used for socketed and HTTP connections. This is particularly useful if you have SSL certificates bound to a particular IP address.

set the defaultNetworkInterface to "192.168.1.10"

It should be in the form of an IPv4 address. If **the defaultNetworkInterface** is not a valid interface, an error will be present in **the result** of the connection attempt. If **the defaultNetworkInterface** is empty, the standard interface will be used.

## Mac - revBrowser userAgent property (4.6.2)

You can now set the UserAgent header presented by a revBrowser instance on Mac. To do so, use:

revBrowserSet instanceId, "useragent", newUserAgent

If *newUserAgent* is non-empty, the browser instance will use that string instead of the default for the User-Agent header transmitted to the web server. If *newUserAgent* is empty, the browser instance will use the default user agent string (which is determined by the browser and URL that is being requested).

To fetch the current user agent setting use:

revBrowserGet(instanceId, "useragent")

Note that this returns empty if you have not set a custom user agent string.

## Print to PDF document outline support (4.6 – improved 4.6.1)

You can now create a document outline in PDFs generated by the pdf printing commands. Individual entries in the document outline are referred to as 'bookmarks' and can be created with the following syntax:

```
print [ unicode ] bookmark title [ with level level ] [ at location ] [ initially ( open | closed ) ]
```

Here *title* is the name of the bookmark which will be displayed, *level* is the depth at which the entry should be placed, and *location* is a point describing where on the current page the bookmark should refer to.

If the unicode adjective is specified, then *title* will be interpreted as a UTF-16 encoded string, otherwise it is interpreted as the native (single-byte) text encoding.

If *level* is not present, then the entry is inserted at the level of the previously inserted item, defaulting to the top-most level if no previous entries have been made.

If *location* is not present, the top-left of the current page will be taken as the location.

If an initially clause is present, it determines the default 'open' state of the bookmark item. Bookmarks are, by default, open. (4.6.1)

## Mac – revCapture video capture library (4.6.1 – experimental)

The revCapture library is begin developed as a replacement for revVideograbber – utilising the most up to date APIs on each platform, and eliminating many issues the previous library had (including problems introduced by Apple with iSight video-capture in 10.6.5 onwards).

At this time, the revCapture library is Mac-only, and is integrated as part of the revVideograbber external; it will be moved into its own external and become cross-platform over time.

While largely similar in function to revVideograbber, the revCapture library does have a number of differences:

- There are no configuration dialogs instead, available inputs and codecs can be queried and configured through script.
- Previewing and recording can be started and stopped independently.
- Previewing takes place direct into a (configurable) image object, allowing the preview to be rendered with effects, blending, inks and interleave with other objects.
- Only supports output to QuickTime MOV files with a limited collection of preconfigured codecs.

The available handlers are described in the following sections.

**Note:** As it stands the revCapture library has only been tested with built-in iSight hardware, although there is no reason it shouldn't work with any hardware that QTKit supports.

Important: This feature is currently experimental. This means that it may not be complete, or may fail in some circumstances that you would expect it to work. Please do not be afraid to try it out as we need feedback to develop it further.

## Session management

All capture operations take place within a capture session, which is managed using:

revCaptureBeginSession

revCaptureEndSession

Call **revCaptureBeginSession** to initialize the capture session, allowing the rest of the capture library to be used. When the capture session is done with, call **revCaptureEndSession**. This will release any hardware, and cancel any recording and previewing operations.

**Note:** Calling any of the revCapture functions without calling **revCaptureBeginSession** at some point before hand will cause a no session error to be thrown.

## Input configuration

Unlike revVideograbber, configuration of the inputs to use for video/audio capture is done entirely through script rather than invoking standard dialogs.

#### Querying available inputs

To query the currently available inputs capable of capturing audio or video data use:

revCaptureListAudioInputs()
revCaptureListVideoInputs()

These both return a newline-delimited list of the available inputs of the given type.

### Configuring the audio input

To configure the audio input to capture from in the current session, use:

revCaptureGetAudioInput()

 ${\bf revCapture Set Audio Input}\ audio Input$ 

Where *audioInput* is one of:

- the name of an input returned by revCaptureListAudioInputs()
- *default*, indicating the default audio input device on the system should be used
- none, indicating that no audio should be captured

If setting an audio input fails because the new device could not be accessed, a *could not open input* error is thrown. If the current session could not connect to the new device, a *could not connect to input* error is thrown.

#### Configuring the video input

To configure the video input to capture in the current session, use:

revCaptureGetVideoInput()

 ${\bf revCapture Set Video Input}\ video Input\ video Input$ 

Where *videoInput* is one of:

- the name of an input returned by revCaptureListVideoInputs()
- *default*, indicating the default video input device on the system should be used
- *none*, indicating that no video should be captured

If setting an audio input fails because the new device could not be accessed, a *could not open input* error is thrown. If the current session could not connect to the new device, a *could not connect to input* error is thrown.

## **Compression configuration**

Similar to input configuration, choosing the codec to use when recording audio and video streams is done entirely through script.

#### Querying available codecs

To query the currently available codecs for audio or video recording use:

revCaptureListAudioCodecs()

#### revCaptureListVideoCodecs()

These both return a newline-delimited list of the available codecs of the given type.

#### Configuring the audio codec

To configure the audio codec to use when recording, use:

revCaptureGetAudioCodec()

revCaptureSetAudioCodec audioCodec

Where *audioCodec* is either *none* to indicate that no audio compression should be performed, or the name of a codec returned by **revCaptureListAudioCodecs()**.

If the given codec name is unrecognized, or is not suitable for audio compression then an *invalid* codec for media type error is thrown. If recording is currently happening, a recording in progress error is thrown.

#### Configuring the video codec

To configure the video codec to use when recording, use:

revCaptureGetVideoCodec()

revCaptureSetVideoCodec videoCodec

Where *videoCodec* is either *none* to indicate that no video compression should be performed, or the name of a codec returned by **revCaptureListVideoCodecs()**.

If the given codec name is unrecognized, or is not suitable for video compression then an *invalid* codec for media type error is thrown. If recording is currently happening, a recording in progress error is thrown.

## **Preview management**

#### Configuring the video preview image

In order to be able to see a video preview of a capture session, the long id of an image object to target needs to be provided. To manage this use:

revCaptureGetPreviewImage()

revCaptureSetPreviewImage imageLongId

Where *imageLongId* is the long id of an existing empty image object to use; or empty to turn off the preview image.

Setting the preview image will lock the corresponding object meaning it can't be resized or have it's content modified by anything apart from the capture session. If the image cannot be found, locked, or an offscreen buffer initialized a suitable error will be thrown.

#### Configuring the audio preview volume

To configure the volume of the audio preview of a capture session use:

revCaptureGetPreviewVolume()

#### revCaptureSetPreviewVolume newVolume

Where *newVolume* is an integer between 0 (no audio preview) and 100 (audio preview at maximum volume).

#### Previewing a session

To start or stop a preview from running use:

#### revCaptureStartPreviewing

#### revCaptureStopPreviewing

The status of the preview is independent to that of recording, meaning that you can preview without recording, and record without previewing.

If a preview of the session could not be initialized when calling **revCaptureStartPreviewing** a *could not connect to output* error is thrown.

**Note:** Starting to record may have an effect on the video preview's aspect and frame size as the video capture pipeline is optimized by the system based on the needs of the recorded output.

## **Record management**

#### Configuring the output file

To configure the filename to use when recording a capture session use:

revCaptureGetRecordOutput()

revCaptureSetRecordOutput recordFilename

Where *recordFilename* is an (absolute) path to the file to use for recording.

If recording is currently in progress, a recording in progress error is thrown.

#### Configuring the maximum frame size

To configure the maximum size of a frame in the recorded file use:

revCaptureGetRecordFrameSize()

revCaptureSetRecordFrameSize maxWidth, maxHeight

Where *maxWidth* and *maxHeight* specify the maximum size of a frame (in pixels) that should be generated in the (compressed) output. To use the default (optimal) frame size for the current settings, specify both width and height as 0.

*Note:* These act as a hint to the pipeline, and the actual size of the frames in the output file may be smaller than this, or have a different aspect ratio.

#### Configuring the maximum frame rate

To configure the maximum frame rate to aim for in the recorded file use:

revCaptureGetRecordFrameRate()

revCaptureSetRecordFrameRate maxFrameRate

Where *maxFrameRate* is the number of frames per second to aim for. To use the default (optimal) frame rate for the current settings, specify the rate as 0.

**Note:** This acts as a hint to the pipeline as to the rate to aim for. The resulting frame rate in the recorded file may be less than, or more than this setting.

#### Starting recording

To start recording the current session use:

### revCaptureStartRecording

This configures the session with previously selected record options and codecs, deletes the currently specified output file (if present) and starts the recording process. It has no effect if the session is already being recorded.

If recording starts successfully, **the result** is empty.

If an error occurs when the output file is being prepared for recording, **the result** will contain *recording failed*.

If the session could not be configured for recording, a *could not connect to output* error is thrown.

### Stopping recording

To stop recording the current session use:

#### revCaptureStopRecording

This finishes outputting any pending samples to the output file and stops recording. It has no effect if the session is not currently being recorded.

If recording finished successfully, **the result** is empty.

If an error occurs while trying to finish writing the output file, **the result** will contain *recording failed*.

## Object snapshot with effects (4.6)

The import and export snapshot commands have been augmented with the ability to specify whether graphic effects and the blendLevel should be applied to the object before rending.

The revised syntax of these commands is:

```
import snapshot from [ rectangle rectangle of ] object [ ( with | without ) effects ] export snapshot from [ rectangle rectangle of ] object [ ( with | without ) effects ] ...
```

Where ... denotes the usual possible suffixes for the export snapshot command.

If the effects clause is not specified, then the object is rendered without effects.

When rendering with effects *rectangle* is clipped to the maximum rectangle the object needs to fully render all the applied effects (this may be considerably bigger than the object, is a distant drop-shadow is involved).

## Print to PDF link improvements (4.6)

The syntax for the 'print link' command has been changed to:

print link to [ url | anchor ] link with rect rectangle

If the url adjective is specified, then *link* will be interpreted as a URI and will create an external URI launching link in the PDF document.

If the anchor adjective is specified, then *link* will be interpreted as an internal anchor name and will create an internal anchor link in the PDF document.

If no adjective is specified then *link* will be interpreted as a URI if it begins with (ASCII) letters followed by a colon. e.g. "<u>mailto:foobar</u>" would be interpreted as a URI, whereas "mail-to-anchor:foo" would be interpreted as an anchor name.

## Field 'plain text' properties (4.6)

Several field properties related to plain text export have been added or updated in the field object.

The *formattedText* and *unicodeFormattedText* properties return the contents of the field as plain text after any wrapping has been performed, where soft (or explicit) line-breaks are exported as a single return character, and paragraph-breaks are exported as two return characters. Any paragraphs with listStyle set get prefixed by an appropriate plain-text form of the bullet or index.

The *plainText* and *unicodePlainText* properties return the contents of the field as plain text with any listStyle properties being converted appropriately into plain-text for the paragraphs they affect.

In both cases the unicode property variants return text encoded in UTF-16 in host byte-order, where as the non-unicode properties return the text encoded in the native platform encoding (with '?' replacing any non-convertible characters).

## Out-of-bounds group scrolling (4.6)

It is now possible to configure a group to turn off automatic clamping of scroll offsets when scrollbars are not present. To control this use the following properties:

set the unboundedHScroll of group to booleanValue

set the unboundedVScroll of group to booleanValue

When an unbounded scroll property is set to true and the corresponding scrollbar is not visible, it is possible to set the scroll for that axis to values outside that of the size of the content (both positive and negative).

The main motivation for this change is to allow much easier implementation of the 'bouncing' effect common in iOS controls. Indeed, after setting the relevant unbounded scroll properties, it is enough to just use the scroll value provided by a scroller object directly as the value passed to the relevant group scroll property.

If a scrollbar is made visible or unbounded scroll is turned off and the corresponding scroll property is outside of the content bounds, the group is scrolled to bring the value within the appropriate range.

## Cryptographic-quality random data (4.6)

A **randomBytes()** function has been added to enable generation of arbitrary amounts of cryptographic-quality random data. To use this feature, the syntax is:

```
randomBytes(byteCount)
```

The function will return *byteCount* random bytes and uses the OpenSSL library's random data generator to do so.

The random data is derived from non-predictable sources where possible, meaning that it can (for the most part) be considered truly random. This is contrast to the **random** function which uses a pseudo-random number generator and **randomSeed** value.

**Note:** Make sure the security library is included when building applications that use this function as a standalone. If the library cannot be found at runtime, the function with throw an error.

## SHA-1 digest support (4.6)

The SHA-1 digest of a block of data can now be computed by using the following form:

```
the sha1Digest of data sha1Digest(data)
```

This function returns the sha-1 digest in the form of 20 (binary) bytes.

## Public key encryption support (4.6)

The **encrypt** and **decrypt** commands now support RSA public key encryption. The new forms supporting this are:

```
encrypt message using rsa with (public | private) key key [and passphrase passphrase] decrypt message using rsa with (public | private) key key [and passphrase passphrase] Here key should be in PEM format, optionally protected by passphrase.
```

The maximum length of a message that can be encrypted using RSA is the size of the key in bytes – 11. So, for a 512-bit key pair, the maximum encryptable message size is 53 bytes.

## Generating key pairs

Public-private key pairs can be generated using the **OpenSSL** suite of command-line tools. For example:

```
openssl genrsa -out private_key.pem 512
openssl rsa -pubout -in private key.pem -out public key.pem
```

Will generate a key pair of size 512-bits, placing the private key in *private\_key.pem* and the public key in *public key.pem*.

For more information on these utilities see <a href="http://www.openssl.org/docs/apps/rsa.html">http://www.openssl.org/docs/apps/rsa.html</a> and <a href="http://www.openssl.org/docs/apps/genrsa.html">http://www.openssl.org/docs/apps/genrsa.html</a>.

#### **Command variants**

Use encrypt with a public key to encode a message that you only want to be decoded the holder of the private key.

Use decrypt with a private key to decode a message that a sender has encrypted with its corresponding public key.

Use encrypt with a private key to encode a message that a receiver can then verify has come from one of the holders of the private key (this is a *signing* operation).

Use decrypt with a public key to verify that a message has been encoded with the corresponding private key, and there has come from one of its holders (this is a *verify* operation).

## **Encrypting longer messages**

For signing, the maximum length of an encryptable message isn't really an issue since typically in that scenario it will be some sort of hash that would be being encrypted.

For the more traditional encrypting scenario, however, the standard approach is to use public key cryptography to encrypt a random password which is then used with a symmetric cipher to actually encrypt the payload.

## Mac – window modification indicator (4.6)

Standard Mac document windows typically display the modified state of the document they represent by adding a dark dot to the close-box. It is possible to control the display of this dot in LiveCode by using:

set the modifiedMark of stack to booleanValue

The indicator will be displayed when the property is set to *true*.

This property has no effect on Windows nor Linux.

## XML text node access (4.6 – experimental)

Support has been added to some revXML functions for manipulating text nodes. Consider the following XML fragment:

```
<summary>
```

Removes a <keyword>message</keyword> that was queued with the <command>send</command> command and is waiting to be sent.

```
<summary>
```

This has the following structure as an XML tree:

```
ELEMENT(summary)

TEXT(Removes a)

ELEMENT(keyword)

TEXT(message)

TEXT( that was queued with the )
```

```
ELEMENT(command)

TEXT(send)

TEXT( command and is waiting to be sent.)
```

Notice that the named XML nodes, are interspersed with (essentially unnamed) nodes containing text content. These (previously unaccessible) nodes can now be accessed (with some functions) by using a path of the form:

```
<parent>/[<index>]
```

Here this references the <n>th text node under <parent>. For example, the above tree has the following accessible nodes:

```
summary/[1]
summary/keyword
summary/keyword/[1]
summary/[2]
summary/command
summary/command/[1]
summary[3]
```

To access text content of a node simply use the *revXMLNodeContents* function with this extended path format. Note that the previous behavior is preserved – if you specify a node with a '/[n]' suffix, the text content of the node will be returned (if it is a text node). (i.e summary/keyword and summary/keyword/[1] are the same thing to *revXMLNodeContents*).

The following functions have been augmented with an additional (optional) parameter *incText*:

```
revXMLFirstChild(docId, [ incText ])
revXMLNextSibling(docId, nodePath, [ incText ])
revXMLPrevSibling(docId, nodePath, [ incText ])
revXMLChildNames(docId, nodePath, delimiter, filter, incCounts, [ incText ])
```

Here if *incText* is specified and is *true*, the functions will include text nodes in their processing. For example, this allows you to loop over all nodes *including text nodes* using something like:

Important: This feature is currently experimental. This means that it may not be complete, or may fail in some circumstances that you would expect it to work. Please do not be afraid to try it out as we need feedback to develop it further.

## Ordered and unordered lists (4.6 – experimental)

### **Properties**

Experimental support has been added to the field for simple, single level, ordered and unordered lists. To make a paragraph display as an element in a list use the *listStyle* property:

#### set the listStyle of line lineIndex of field to style

Where *style* is one of:

- *disc* the paragraph is rendered as an element in an unordered list with the standard bullet character as marker (U+2022).
- *circle* the paragraph is rendered as an element in an unordered list using the (unicode) character U+25E6 as marker.
- *square* the paragraph is rendered as an element in an unordered list using the (unicode) character U+25AA as marker.
- *decimal* the paragraph is rendered as an element in an ordered list, the label using standard (Arabic) decimal numerals. i.e. 1, 2, 3, 4, etc.
- *lower latin* the paragraph is rendered as an element in an ordered list, the label using lowercase (Latin) letters. i.e. a, b, c, ..., aa, ab, etc.
- *upper latin* the paragraph is rendered as an element in an ordered list, the label using uppercase (Latin) letters. i.e. A, B, C, ..., AA, AB, etc.
- *lower roman* the paragraph is rendered as an element in an ordered list, the label using lowercase Roman numerals. i.e. i, ii, iii, iv, ..., etc.
- *upper roman* the paragraph is rendered as an element in an ordered list, the label using lowercase Roman numerals. i.e. I, II, III, IV, ..., etc.

For both ordered and unordered list the marker is placed at the first tab-stop, and the content of the paragraph is placed (and wraps) at the second tab-stop.

For ordered lists the index of the item is determined by the number of preceding paragraphs with the **same** *listStyle* property.

Setting the *listStyle* property of a paragraph to empty causes it to revert to a normal (non-list item) paragraph.

#### htmlText format

Paragraphs with a non-empty *listStyle* present themselves in *htmlText* wrapped with *<LI>* tags. Sequences of such paragraphs with the same *listStyle* are bracketed by *<UL>* or *<OL>* tags. These tags take a *type* attribute, matching the (legacy) HTML attribute of the same name:

- $disc \rightarrow disc$
- $circle \rightarrow circle$
- $square \rightarrow square$
- $1 \rightarrow decimal$

- $a \rightarrow lower\ latin$
- $A \rightarrow upper \ latin$
- $i \rightarrow lower\ roman$
- $I \rightarrow upper roman$

#### For example:

2.	Numbered Item 1 Numbered Item 2 Bulleted Item 1	<pre><ol type="1">   <li>Numbered Item 1</li>   <li>Numbered Item 2</li>   </ol></pre>
•	Bulleted Item 2	<pre><ul type="disc"> <li>Bulleted Item 1</li> <li>Bulleted Item 2</li> </ul></pre>

#### rtfText format

Paragraphs with a non-empty *listStyle* are appropriately marked in *rtfText* using both the (legacy) *pn* family of paragraph numbering tags and also with the new *listtable* tags.

By using both sets of tags a reasonable degree of interoperability is achieved with both TextEdit (and other Cocoa applications) on Mac, and Word and WordPad on Windows.

**Note:** Unfortunately, OpenOffice does not have particularly good rtf import / export capabilities (it doesn't even round-trip correctly through itself!) and thus copying / pasting of lists between LiveCode and OpenOffice will not work reliably or correctly.

## plainText format

Paragraphs with a non-empty *listStyle* are appropriately exported in plain text form when using the *plainText*, *unicodePlainText*, *formattedText* and *unicodeFormattedText* properties.

For example, the above example would be rendered (for plainText) as:

```
<tab>1.<tab>Numbered Item 1<return>
<tab>2.<tab>Numbered Item 2<return>
<tab>•<tab>Bulleted Item 1<return>
<tab>•<tab>Bulleted Item 2<return>
```

#### **Persistence**

As it stands the *listStyle* property does not save into the stack-file and will not do so until version 5.0 when the file format is revised (for various technical reasons, it is not possible to add this as a saveable property with the current stackfile format).

It is recommended that htmlText be used to save the content of fields in custom properties, for restoration on reload

Important: This feature is currently highly experimental. This means that it may not be complete, fail in some circumstances that you would expect it to work, or change considerably before becoming final. Additionally, it might have problems or gotchas that make it significantly harder to use than other LiveCode features at this time.

## XML Namespace support (4.5.1)

By default, revXML will process XML Namespace related tags and attributes in a way that is inaccessible to revXML. This can cause problems when a script needs to process the namespaces itself.

To resolve this issue two additional functions mimicking the behavior of revCreateXMLTree and revCreateXMLTreeFromFile have been added to revXML. These functions are:

```
revCreateXMLTreeWithNamespaces
revCreateXMLTreeFromFileWithNamespaces
```

The difference between these and the originals is that these two functions ignore namespace tags and attributes, and instead return them as part of the tree without doing any processing.

For example, consider the following XML tree:

Will get interpreted as follows:

#### revCreateXMLTree

#### revCreateXMLTreeWithNamespaces

```
db
                                         db
 record[1]
                                           bb:record[1]
   record[1]/firstname
                                             bb:record[1]/bb:firstname
   record[1]/lastname
                                            bb:record[1]/bb:lastname
   record[1]/zip
                                            bb:record[1]/zz:zip
 record[2]
                                           xx:record[2]
   record[2]/firstname
                                            xx:record[2]/xx:firstname
   record[2]/lastname
                                            xx:record[2]/xx:lastname
   record[2]/zip
                                            xx:record[2]/xx:zip
```

The latter form is more appropriate in the case that an application needs the namespace information to perform correctly.

## Runtime execution stack configuration (4.5.1 – experimental)

In order to be able to more reliably control the maximum level of recursion, a new global property **stackLimit** has been introduced.

This property allows a script to set (in bytes) the maximum size of the (runtime) stack the engine uses for recursive computation. A change in the setting will only take effect when all currently executing handlers complete, and at this time the stack size limit will be reconfigured to the given limit, or the nearest amount to it depending on available memory.

The stackLimit currently in effect can be fetched using the effective stackLimit.

The recursionLimit property is now bounded by the stackLimit – attempts to set the recursionLimit greater than the stackLimit will see it downwardly adjusted to the maximum current size allowed.

**Note:** The changes to the recursionLimit property and the new stackLimit property are only implemented on Windows at present.

Important: This feature is currently experimental. This means that it may not be complete, or may fail in some circumstances that you would expect it to work. Please do not be afraid to try it out as we need feedback to develop it further.

## revBrowser windowld property (4.5.1 – experimental)

There is a long standing issue with revBrowser that causes browser instances to be lost whenever the stack it is attached to has its window re-created. Previously, cases where this would occur had to be avoided when a browser was present on a stack.

To resolve this problem a new property has been added to browser instances – windowId. The windowId property allows the stack to which a browser instance is attached to be changed after it has been created.

If the windowId is set to 0, the browser instance is temporary hidden. If the windowId is set to a valid stack windowId, the browser instance will move to that stack.

For example, to toggle the resizable property of a stack hosting a browser use the following code:

revBrowserSet pBrowserId, "windowId", 0

set the resizable of stack pBrowserStack to pNewResizeableValue

revBrowserSet pBrowserId, "windowId", the windowId of stack pBrowserStack

Important: This feature is currently experimental. This means that it may not be complete, or may fail in some circumstances that you would expect it to work. Please do not be afraid to try it out as we need feedback to develop it further.

## Non-blocking DNS resolution (4.5)

The **open socket** command no longer blocks on DNS resolution. Instead, if resolution is required the command will return immediately and the DNS lookup will happen in the background. If resolution fails, then a **socketError** message is sent in the same was as if connection fails.

For applications using **hostNameToAddress** directly, its syntax has been augmented:

hostnameToAddress(hostname, [ callback ])

If the *callback* parameter is specified then the call will return immediately and upon completion of the lookup, the callback will be invoked with the resolved address as a parameter.

# Improved cursor support (4.5)

Cursor support has been improved in several ways.

The image will now automatically process any image to convert to a form suitable for display on the current platform and screen depth taking this burden off the developer. Specifically, the engine will scale the image down to the appropriate size, and reduce the number of colors to the appropriate number of colors.

Additionally, the engine has been updated to take advantage of support for larger and potentially alpha-blended cursors on platforms that support this. Specifically:

- Windows XP and above support full alpha-blended cursors up to 64x64
- More recent Linux distributions support alpha-blended cursors up to a size of 64x64
- Mac supports alpha-blended cursors up to 256x256

The engine now picks up the GTK cursor theme on Linux. (4.5.1)

**Note**: It appears that alpha-blending support depends on the current screen depth on some platforms.

## Improved image export (4.5)

### **BMP Export**

The export command can now produce Windows BMP format images in the same was at it previously did for gif and png:

export target as bmp

#### Palette reduction

The **export** command can now perform color reduction. To support this, the following new forms have been added:

```
export target as ( gif | png | bmp ) with palette colors
export target as ( gif | png | bmp ) with ( standard | optimized ) palette
export target as ( gif | png | bmp ) with count color optimized palette
```

The first form allows you to specify a list of up to 256 colors to use in the final palette.

The second form will use either the standard 'websafe' palette, or will compute an optimized palette with at most 256 colors.

The third form allows you to choose the size of the optimized palette to be generated. The number of colors can be at most 256.

If the image has any sort of transparency, then this will utilize one palette entry. (In particular if you ask for a 256 color palette with a transparent image, you may get only 255 colors).

In all cases, optional dithering will be performed as determined by its **dontDither** property.

**Note:** It is a (relatively) slow process to compute an optimized palette and then remap an image against it - it should not be considered a real-time operation except for very small images.

**Note:** There is no support for exporting a JPEG with a reduce palette as this format is for continuous-tone images and as such the notion of palette makes no sense.

## Raw data export (experimental)

It is possible to export raw image data using the following forms:

```
export target as raw with palette colors

export target as raw with ( standard | optimized ) palette

export target as raw with count color optimized palette

export target as raw [ argb | bgra | abgr | rgab ]
```

The first three of these operate in the same way as for the other formats as described above except that instead of formatted image data you get the raw palette indices packed appropriately depending on the size of the palette:

```
<= 2 colors will be 1 bpp
<= 4 colors will be 2 bpp
<= 16 colors will be 4 bpp
<= 256 colors will be 8 bpp
```

The final form allows export of the full 32-bit data of the image with 8 bits per component. In this case, the components are not pre-multiplied with any alpha channel, and appear ordered in memory in increasing bytes.

```
e.g. The argb form will give you:
byte 0 = alpha
byte 1 = red
byte 2 = green
byte 3 = blue
```

Important: This feature (raw data export) is currently experimental. This means that it may not be complete, or may fail in some circumstances that you would expect it to work. Please do not be afraid to try it out as we need feedback to develop it further.

## Color profile support (4.5)

The engine will now attempt to use any embedded ICC color profile information that is present in JPEGs and PNGs.

If a JPEG contains a color profile then the engine will attempt to use it to translate the image's colors to the default screen color space before display.

When printing JPEGs, the original JPEG data will now be sent to the printer directly whenever possible, In particular, this means that any intermediate color matching for the screen that the engine performs does not affect the printed output.

As an additional side-effect of color profile support, the engine now also supports YCCK and CMYK JPEG images.

Note: Support for color profiles depends on the OS - in particular Windows XP and earlier only support ICC v2 profiles, Vista onwards supports ICC v4.

## Print to pdf support (4.5)

The engine printing system has been augmented with the ability to *print to pdf*. This feature uses the existing print-loop model and virtually no code changes are needed to make existing code use it.

## **Print loop integration**

To start a print loop that outputs directly to a pdf rather than the currently configured printer, use the following form:

open printing to pdf filename [ with options optionArray ]

This should be performed *instead of* the usual **open printing** command.

**Note:** It is not necessary (and unwise!) to set the **formatForPrinting** option on stacks which are being printed to PDF.

## **Options**

The options array which can be optionally specified when opening a print loop for pdf allows you to add entries to the resulting PDF's *Document Information Dictionary*.

The following keys are supported:

Title, Author, Subject, Keywords, Creator, Producer

Their values can be any string.

## **Hyperlink support**

When inside a pdf print loop you can use additional commands to define hyperlinks and their targets.

To define a target for an internal hyperlink, use the following form:

print anchor name at anchorPoint

Here *name* is used to identify the anchor in related **print link** commands, and *anchorPoint* is the location on the current page to which any such link should jump to.

To define a hyperlink use the following form:

print link to target with rect linkRectangle

If *target* is a url, then the given rectangle will jump to that url when it is clicked. If *target* is not a url, it is assumed to be the name of an internal anchor as specified by the **print anchor** command and clicking in the given rectangle will jump there instead.

When printing fields, any text that has its **linkText** property set and has the textStyle **link** set will be treated as if a **print link** command had been executed with the contents of the property as target, and the formattedRect of the text as rectangle.

## **Runtime dependency**

The implementation of pdf printing resides in a dynamic library called *revpdfprinter*. The standalone builder will automatically include this in the appropriate place when building standalones.

Any custom code that deals with standalones which use this feature must make sure that the revpdfprinter library resides next to the engine executable (On Mac, this is inside the Contents/MacOS folder, not next to the bundle).

## Slave process improvements (4.5)

A number of issues with the *open process* command and the engine itself have, up until now, conspired to make it difficult (if not impossible!) to either run a slave process, or use the engine as slave on all platforms.

These issues have been resolved in this version, thus making it straightforward to run another process and poll for input and output over stdin/stdout.

The typical form for this is along the following lines (this example assumes the process being executed outputs whole lines):

```
command startSlave pProcess
       open process pProcess for text update
       send "monitorSlave pProcess" to me in 50 millisecs
end startSlave
command monitorSlave pProcess
       repeat forever
              # Loop until there are no more lines to read.
              read from process pProcess for 1 line in 0 millisecs
              if the result is empty then
                      # The slave has sent us something, so process it and loop for
                      # (potentially) more data.
               else if the result is "timeout" then
                      # There is nothing waiting for us, so exit repeat
                      exit repeat
               else if the result is "eof" then
                       # The slave has terminated, so do any final processing and finish
                      # monitoring.
                      close process pProcess
                      exit monitorSlave
               else
                      # Some error has occurred!
                      exit monitorSlave
              end if
       end repeat
       send "monitorSlave pProcess" to me in 50 millisecs
end monitorSlave
```

## Videograbber improvements (4.5)

Some work has been done on storing and fetching settings from the videograbber.

On Windows and Mac, audio and video settings are now correctly retrieved and set using revVideoGrabSettings and revSetVideoGrabSettings.

On Windows (when using DirectShow), the 'Camara Control' settings are now saved and restored via the grab settings commands. Specifically: pan, tilt, roll, zoom, exposure, iris, focus and flash.

## Elevated process support (4.5 – experimental)

Sometimes it is necessary to perform operations on the local machine as an administrator, and a typical pattern for a GUI application doing this is for it to prompt for authentication at certain points.

Modern operating systems do not permit a process to elevate itself, nor grant itself increased privilege. Instead, they only allow a running process to launch another process with increased privilege. Therefore, in order to support this, a new form of the **open process** command has been introduced that can launch a slave process with elevated permissions:

open elevated process process [ for [ text | binary ] ( read | write | update | neither ) ]

This form operates identically to the normal version, except that engine will ask the system to launch the given process with admin/root privileges.

The standard way for a GUI application that needs to perform privileged operations to be structured is to split the application into two parts: a GUI front-end that interacts with the user, and a command-line back-end that is run with elevated permissions. These two parts can then talk to each other using a standard master-slave approach, or some other form of IPC such as sockets.

Important: This feature is currently experimental. This means that it may not be complete, or may fail in some circumstances that you would expect it to work. Please do not be afraid to try it out as we need feedback to develop it further.

### Status icon support (4.5 – experimental)

Windows, Linux and Mac all have an area where so-called 'status icons' can be displayed. On Windows this is the system tray on the bottom right of the start bar, on Linux this is typically the right of the panel at the top of the screen, and on Mac this is on the menubar.

The engine has support for adding a single status icon, and it can be configured using the statusIcon, the statusIconTooltip and the statusIconMenu:

set the statusIcon to imageId set the statusIconMenu to iconMenuSpec set the statusIconToolTip to toolTip

Here *imageId* is the id of the image you wish to use as the icon. It will be scaled down automatically to the appropriate size for the platform and then set. The *toolTip* specifies what message appears when the user hovers over the status icon.

The *iconMenuSpec* allows you to configure a menu that will appear when the user does a 'menu' click on the icon. This string uses a subset of the standard engine menu specification:

Here the number of tabs determines the depth of the menu (i.e. use this to create sub-menus). The optional tag is used when calling the **statusIconMenuPick** message.

Before the engine displays the status icon menu, it will send a **statusIconMenuOpening** menu to the current card of the defaultStack. You can use this opportunity to change the icon menu before it is displayed, this is an analog to handling *mouseDown* in a menu button.

When the user selects an item from the dock menu, the engine will send an **statusIconMenuPick** message to the current card of the default stack:

#### iconMenuPick which

Here *which* will be a list of labels or tags (if specified) separated by "which determines which item was selected.

In addition, the engine will send the following message in response to clicks on the icon:

statusIconMenuClick button

statusIconMenuDoubleClick button

You can use these to perform an appropriate action.

**Note:** If you wish to display a menu from the status icon you must use the statusIconMenu property, attempting to open a normal popup menu in response to one of the click messages is not guaranteed to work.

**Note:** This syntax is only implemented on Windows at the moment and replaces the previously unsupported use of **the icon** and **the iconMenu** for this purpose. The properties specified above will have no effect on Mac and Linux at this time.

Important: This feature is currently experimental. This means that it may not be complete, or may fail in some circumstances that you would expect it to work. Please do not be afraid to try it out as we need feedback to develop it further.

## Listing sub-keys in the registry (4.5 – experimental)

To get a list of sub-keys in the Windows registry use the following function:

listRegistry(parentKey)

This will return a return-delimited list of sub-keys, i.e. those keys which are direct children of the given *parentKey*. The specified key should be in the same format as the other registry functions.

Important: This feature is currently experimental. This means that it may not be complete, or may fail in some circumstances that you would expect it to work. Please do not be afraid to try it out as we need feedback to develop it further.

## HTTPS – automatic root certificate discovery (4.5 – experimental)

In previous versions it was necessary to set the *sslCertificates* property to the root certificates that HTTPS connections should be verified against. Support has now been added to locate and load the root certificates installed (and kept up to date) as part of the OS.

This uses the standard root certificate keychain on Mac, the standard root certificate store on Windows and uses a number of heuristics to locate this information on Linux.

You can easily find out if the system-installed root certificates are being found by running the following command in the message box:

get url "https://www.google.com"

#### put the result & return & it

If this results in an error about verification failure then it is likely that root certificates have not been found. Please let us know (particularly on Linux) if you find this simple test fails, making sure you give us full details of your system (e.g. Linux distribution and version).

**Note:** Unfortunately this feature does not currently work correctly on Mac 10.6.x. For now, we advise including an appropriate root certificates collection with your application, as was previously necessary, and setting the **sslCertificates** property appropriately.

Important: This feature is currently experimental. This means that it may not be complete, or may fail in some circumstances that you would expect it to work. Please do not be afraid to try it out as we need feedback to develop it further.

## Mac – dock icon support (4.5 – experimental)

Previously unsupported syntax for manipulating the dock icon on Mac is now experimental.

## Choosing an image

The current dock icon image can be set by using the global **icon** property:

#### set the icon to imageId

The engine will attempt to find an image with the given id, resize it to 128x128 and then set it as the dock icon for the application.

This property has no effect on other platforms.

*Note:* The image is only guaranteed to persist while the application runs, although in some cases the OS does appear to cache it beyond this.

## Configuring the dock icon menu

In addition to changing the dock icon image, you can also configure the menu that appears when the user clicks on it.

To set the dock icon menu use the global **iconMenu** property:

#### set the iconMenu to iconMenuSpec

Here, *iconMenuSpec* is a string describing the menu. This uses a subset of the standard menu specification syntax. The string should be a return-delimited list of items specified as follows:

Here the number of tabs determines the depth of the menu (i.e. use this to create sub-menus). The optional tag is used when calling the **iconMenuPick** message.

Before the engine displays the icon menu, it will send a **iconMenuOpening** menu to the current card of the defaultStack. You can use this opportunity to change the icon menu before it is displayed, this is an analog to handling *mouseDown* in a menu button.

When the user selects an item from the dock menu, the engine will send an **iconMenuPick** message to the current card of the default stack:

#### iconMenuPick which

Here *which* will be a list of labels or tags (if specified) separated by '|' which determines which item was selected.

Important: This feature is currently experimental. This means that it may not be complete, or may fail in some circumstances that you would expect it to work. Please do not be afraid to try it out as we need feedback to develop it further.

#### Maintenance

## **Noteworthy changes**

The following bug fixes or changes are ones which may have an impact on existing code and/or may be important to a wide audience.

(changes specific to the current build are highlighted with a gray background)

#### Mac OS 10.3.9 is no longer supported

Support has been dropped for Mac OS 10.3.9.

#### Clipboard format for styled-text on Mac now RTF

The styled text format that LiveCode exports to the clipboard on Mac has been updated to be RTF – this brings it inline with both Windows and Linux, and will allow support for hyperlinks and listStyles to be supported in a subsequent build.

#### SQLite updated to 3.7.4 with Full Text Search enabled

The verison of SQLite compiled into dbSqlite has been updated to version 3.7.4. In addition, the 'FTS' feature has been compiled in. For more information about this version of SQLite and the FTS feature please see the documentation at <a href="http://www.sqlite.org">http://www.sqlite.org</a>.

#### Non-character keys can cause erroneous keyDown messages on Mac

Previously keys such as page-up, page-down and the function keys would cause keyDown messages to be sent to a field but with a nonsensical parameter. These keys no longer generate keyDown in line with other platforms.

### The listStyle property has better RTF import / export support

Support for both types of list specification in RTF has been added, increasing interoperability with other applications when using the clipboard. See the section on the listStyle feature for more information.

#### Bug 818 – About item always present and enabled on Mac

The engine will now only add an *About* item to the Apple menu if it finds a menu with name *Help* whose last item has tag *About* or label beginning with *About*.

Furthermore, the about item is enabled only if the found item is enabled and the help menu is enabled.

#### **Bug 3071 – Preferences item cannot be disabled on Mac**

The engine will now only enable the Apple menu preferences item if the following are all true:

- There is a menu with name *Edit*
- The edit menu is enabled
- The last item of the edit menu has tag *Preferences*, or has label beginning with *Preferences*
- The preferences item is enabled

#### Bug 1197 – backgroundBehavior policy now enforced

The engine now strictly enforces the following two rules:

- a nested group cannot have the backgroundBehavior set to true
- a group placed onto multiple cards cannot have its backgroundBehavior set to false

On loading stacks in the IDE, a consistency check will be performed which will result in these rules holding after load.

#### **Bug 2122 – Styled text overruns tab-stops**

You can now use styled text correctly when a field has the *vGrid* property turned on. The text will be clipped correctly at cell boundaries.

#### Bug 4026 – importing images > 4091 wide causes corruption on Mac

The long standing limit on the width of image objects on Mac has been lifted. Images are now limited by available memory, rather than the width.

#### Bug 7334 – rtfText output is now effective

The rtfText property is now 'effective' in the sense that it contains styling for all characters, including those which inherit text properties from the field (or more distant ancestor). This change has been made to make it more useful for clipboard export. If you wish to fetch the contents of the field with the inheritance structure intact, use the htmlText instead.

#### Bug 9301 – menuHistory now has consistent behavior for all menu button types

Previously, setting the menuHistory would only work reliably for option/combo buttons. This has been rectified and setting the menuHistory (or using select menuitem ... of menu ...) will now cause the correct *menuPick* message to be dispatched for all menu button types.

Note that for option and combo buttons, such a message will only be sent if the menuHistory changes, this is consistent with these objects having a notion of 'currently selected item'.

#### Bug 9378 - 'mailto:' URLs not recognized by 'print link to'

In order to better support usage, the syntax and functionality of the 'print link' command has changed. In particular, the print link command now accepts a 'url' adjective to better specify the type of link. This will require changes to existing scripts in a very specific case.

Code such as:

```
print link to url "file:mylinktext.txt" with rect tMyLinkRect
```

Needs to be changed to:

```
print link to (url "file:mylinktext.txt") with rect tMyLinkRect
```

#### Bug 9412 – Messages passing through a background are received twice if passed

The message path order for backgrounds has been revised slightly (in a backwards-compatible fashion) to take proper account of passing of messages. For a control within a background, the message path is the following:

```
target's owning groups
target's background
card
card's backgrounds not including the target's background
stack
```

The path for a message sent to a background is:

```
target background
card
card's backgrounds not including the target's background
stack
```

**Note:** The above order effectively means that a background's script is only behind the card for controls it does not contain which retains compatibility with previous interpretations of backgroundBehavior.

## Specific bug fixes (4.6.4)

(bug fixes specific to the current build are highlighted in bold, reverted bug fixes are strickenthrough)

- 9719 Printing does not fully render controls
- 9712 Paint tools don't work correctly on OS X and Linux
- 9721 Certain date calls crash OS X standalones
- 9714 Standalones built with personal licenses crash on launch
- 9703 Crash setting the alpha data of an image when using RLE paint compression
- 9715 Can't specify socket MySQL driver connects with Incorrect font names used when pasting RTF text on Mac
- 9700 Error with setting properties after getting array
- 9698 Crash when setting a property using an empty variable
- 9689 hostNameToAddress causes lock up
- 9691 On Linux, files greater than 2GB always return false with there is a file
- 9685 Repeat for each element crashes for some arrays with binary data
- 9686 The messageMessages property prevents arrays from being returned
- 9676 Cursor not switching back
- 9673 Startup messages not being sent
- 9675 Combo box labels not displaying
- 9668 Send messages not being sent correctly

Run-away memory loop when processing '', '' and '' tags

Chunk expressions don't allow <objehunk> ... of control ...

Cloning a stack results in objects in groups on non-current card with id of zero

Copying group to non-current card causes new group's controls to have id of 0 until that card is opened

Control references of the form <chunk> id ... of stack ... do not work for groups nor nested control/group sequences

Import snapshot not working on Windows when composition enabled (>= Vista with Aero) and multiple monitors present

9507 Setting \*color of image objects inverts red and blue on Windows for palette images

## Specific bug fixes (4.6.3)

Memory leak when setting htmlText with more than 254 images

- 9625 Freeze on entering? into script editor
- 9608 Undirected puts crash LiveCode is message box is not visible
- 9603 Setting the menuHistory of a popup menu with an empty text property crashes IDE
- 9559 Sliders get stuck on -1
- 1533 Substacks see library stacks in message path twice in standalones.

## Specific bug fixes (4.6.2)

Crash when fetching revBrowser 'useragent' property before its been set.

5303 Antialiased graphics don't show single pixels

- 9536 High bit-rate encryption fails on Windows
- 9573 Graphic effects swap red / blue channel on Windows

## Specific bug fixes (4.6.1)

revCaptureSetRecordFrameRate throws an error

- 9483 the tempName can generate non-unique file paths
- 9486 Delay after dropping on Mac
- 9489 Importing 2 color PBMs causes a crash on save
- 9503 Formatted width of listStyle paragraphs is incorrect
- 9504 Focus border remains if focused field disabled by script

## Specific bug fixes (4.6)

Crash when setting the 'id' of a template object

Wrong drag-drop result returned to OS in some cases (causing incorrect snap-back)

Crash when image fails to load due to lack of memory

Underline/strikethrough not displayed in fields in most cases

'repeat for each key' does not preserve loop var value on 'exit repeat'

'print bookmark' doesn't work correctly with non-ASCII titles

The 'formattedText' includes extra linebreaks

Memory leak when displaying some revOnline dialogs.

Incorrect htmlText output for listStyle for last paragraph in field

Unable to fetch 'the listStyle' from field chunks

Border (incorrectly) shows around PDF hyperlinks in Preview

Intermittent problem with text styling when printing as PDF

Crash when cutting card containing a non-background shared group

Copying from dictionary into TextEdit on Mac fails sometimes

Transient parts of objects (e.g. focus borders) do not appear in graphic effects

<BR> in htmlText can cause spurious listStyles to be applied

tags are not optional when in tags

'go as sheet' doesn't disable the parent window on Windows

'ask folder' uses new style dialog on Vista and later

Fonts in styled text can paste with incorrect style on Mac in some cases

Non-character keys can cause erroneous keyDown messages on Mac

Text linkClicked parameter contains an incorrect trailing character in some cases

- About item always present and enabled on Mac
- 1197 Correct setting of backgroundBehavior now enforced.
- 2122 Styled text overruns tab-stops
- 3071 Preferences item cannot be disabled on Mac
- 4026 Importing images > 4091 wide causes corruption on Mac
- 5141 Menus with unicode titles sometimes disappear on non-English systems
- 5869 Fields do not use standard Mac text editing shortcuts
- 7102 Oracle driver not available for Intel
- 7334 'the rtfText' output is not effective (i.e. does not contain styling for inherited runs)
- 7358 Problems with direction specifiers in visual effects
- 7974 'ask file' works incorrectly in some cirumstances on Mac
- 8612 revBrowserRefresh breaks subsequent searches on Windows
- 8790 Driver name should be lower-cased before loading
- 8991 Pending messages not dispatched until mouse moved after drag-drop action

- 9192 'record sound' does not create a file properly if given a relative path
- 9282 'lock messages' not reset after modal dialogs (including answer and ask commands)
- 9284 Double-clicking on a word in a locked field does not select it
- 9288 'the properties' does not take account of an explicit card reference
- 9293 Unicode text causes incorrect table alignment
- 9298 Large linesizes of graphics cause incorrect hit-testing
- 9301 'the menuHistory' has inconsistent behavior for pulldown/popup/cascade menu buttons
- 9308 Ids of controls can only be changes on the current card and crashes otherwise
- 9311 Keys of options passed to revPDFPrinter are not case-insensitive
- 9332 'launch url' doesn't always return to LiveCode
- 9352 The menuHistory of some menu button types not set correctly
- 9353 Rectangle graphics of height 1 don't print to PDF
- 9355 Export snapshot confuses focus of fields
- 9359 Can't quit when revBrowser has focus on Mac
- 9368 CMYK JPEGs don't appear in printed PDFs
- 9375 The 'templateField' does not convert text to htmlText
- 9377 mouseDoubleUp not sent to locked and list fields
- 9378 'mailto:' URLs not recognized by 'print link to'
- 9380 listStyle doesn't report 'mixed' when it should in many cases
- 9381 'export snapshot' does not render anti-aliased text correctly on Windows
- 9382 Radio buttons with custom icons don't update correctly when in backgounds
- 9383 Crash when setting 'the backgroundBehavior' of the templateGroup
- 9384 Unnecessary limit on the number of menu buttons on open cards on Mac
- 9388 Change in how htmlText is interpreted
- 9395 Crash when setting field rect on Linux
- 9396 Tooltips don't have drop-shadows on Windows 7
- 9399 Can't get the short name of the dragSource
- 9400 'the text of the selectedLine' is always empty
- 9403 Right-click then Cut on Mac causes crash on empty image
- 9404 The formattedHeight of a field counts the scrollbarWidth twice
- 9410 Current external load process is dependent on current folder on Windows
- 9412 Messages passing through a background are received twice if passed
- 9413 The ctrlKey synonym is tied to commandKey
- 9417 Only the first link on a line ever activates when listBehavior is true
- 9419 The pixel properties only work if the object is on the current card of an open stack
- 9428 Modal windows do not behave correctly on Linux
- 9435 BMP images with depth < 32 and odd width do not import correctly
- 9439 Text does not render correctly on non-primary screen on Linux (not tested)
- 9447 The linkClicked message does not pass the full linkText value as a parameter
- 9451 Numeric keypad input does not work on Mac
- 9466 Tab key does not insert a tab into fields.

## **IDE Changes**

## Getting folder locations within the IDE

If you write plugins, or have code that relies on the location of IDE files then please ensure you use the following access functions to locate them:

revEnvironmentToolsPath() The location containing the main IDE files. The location of the main IDE stacks. revEnvironmentToolsetPath() The location of the externals that come with the IDE. revEnvironmentExternalsPath() revEnvironmentPluginsPath() The location of the plugins that come with the IDE. The location of the standalones that come with the IDE. revEnvironmentRuntimePath() The location of the documentation files. revEnvironmentDocumentationPath() revEnvironmentResourcesPath() The location of the resources that come with the IDE. The location of the IDE customization folder. revEnvironmentCustomizationPath() revEnvironmentUserCachePath() The location of the folder to use for caching files. revEnvironmentUserPreferencesPath() The location of the folder to use for preference files. revEnvironmentUserExternalsPath() The location of the folder to use for additional externals. revEnvironmentUserPluginsPath() The location of the folder to use for additional plugins. revEnvironmentUserResourcesPath() The location of the folder to use for additional resources.

Important: Third-party IDE extensions must avoid placing any files inside the application bundle or under revEnvironmentToolsPath() (not least because you will probably not have privileges to do so!). Instead, they should use the user-externals and user-plugins paths as provided. These paths are determined by the user's customization path setting, configurable in the preferences.

## Update checker

The update checker and its corresponding menu item in *Help* have been removed. The version checking method is changing, and this option will re-appear in a subsequent release.

## Affiliate registration

The affiliate registration item in the *Help* menu has been removed The method of affiliate registration is changing, and this option will re-appear in a subsequent release.

## Database query builder

Use of the database query builder has been deprecated.

To access its functionality, choose the *Enable database query builder* option on the *Compatibility & Updates* pane of the preferences.

**Note:** The database query builder will be removed entirely in the next or subsequent non-maintenance release.

## Android Support (4.6.1)

The IDE now contains built-in support for testing and deploying Android applications. The

following features have been added to support this:

- An Android pane has been added to the Standalone Builder
- Save as Standalone Application can now build Android applications
- The *Test* button supports both Android and iOS application testing.
- Configuration of the test target (device or emulator) via a *Test Target* submenu in the *Development* menu.
- Configuration of SDK location for Android in the *Mobile Support* pane of the Preferences.

More details on how to use these features can be found in the *Android Release Notes* accessible via the *Help* menu.

**Note:** If you do not have an Android deployment pack, you can still use the Android feature in trial mode. In this case the applications you build will contain a forced banner on startup lasting 5 seconds, and they will quit after one minute.

## *iOS Support (4.5.2)*

The IDE now contains built-in support for testing and deploying iOS applications. The following features have been added to support this:

- An iOS pane has been added to the Standalone Builder
- Save as Standalone Application can now build iOS applications
- A *Test* button has been added to the menubar to enable fast and easy access to running applications in the simulator
- Configuration of simulator version and type can be accessed via a *Test Target* submenu in the *Development* menu.
- A *Mobile Support* pane has been added to the preferences to enable configuration of iOS SDKs (needed by deployment and simulation).

More details on how to use these features can be found in the *iOS Release Notes* accessible via the *Help* menu.

**Note:** If you do not have an iOS deployment pack, you can still use the iOS feature in trial mode. In this case the applications you build will contain a forced banner on startup lasting 5 seconds, and they will quit after one minute.

## Access to resources folder (4.5.2)

The IDE comes with a Resources folder containing the sample projects, example stacks and other miscellany.

Previously this was easily accessible on all platforms by navigation to the installed IDE folder. As this folder is now (on some platforms) inside an application bundle, a new item in the Help menu *Example Stacks and Resources* has been added to open up the folder in the file manager on the running system.

#### Standalone builder

#### Windows - UAC Manifest

It is now possible to specify what action UAC should take on Windows Vista and higher when the standalone is launched. You can choose one of the following options:

Default No UAC option is provided in the manifest.

Save as Invoker The application will run with the same privileges as the process that

invoked it.

Highest available The application will be elevated to the highest privilege level the current

user is allowed.

Require administrator The application will be run as administrator after prompting the user for

appropriate login/elevation rights.

#### Web

Using the 4.5 standalone builder to build for Web will create revlets. These are compatible with the existing revWeb plug-in available from revweb.runrev.com.

An updated version of the IDE for producing LiveCode Applets and the associated LiveCode player will be made available in due course.

**Note:** As the currently available revWeb plug-in uses the 4.0 engine, you must be careful to only use features that are present in that version.

## **Android (4.6.1)**

There is now a pane for configuring Android applications in the Standalone Builder.

More details on how to use the Android settings pane can be found in the 'Android Release Notes' accessible via the Help menu.

## iOS (4.5.2)

There is now a pane for configuring iOS applications in the Standalone Builder. At this time, iOS standalone building has the following limitations (compared to desktop/web deployment);

- A stack configured for iOS cannot also deploy to other non-mobile platforms
- The Copy Referenced Files feature is not implemented for iOS builds.
- The *Inclusions* and *Property Profiles* feature is not implemented for iOS builds.
- The *Stacks* configuration options are not available for iOS builds.

More details on how to use the iOS settings pane can be found in the 'iOS Release Notes', accessible via the Help menu.

## Datagrid

The datagrid is currently at version 1.0.2 (build 14).

1.0.2 (build 12) Added specific scrollbar width for linux platform.

DeleteFieldEditorAndOpenNext now continues looking for a column to edit if EditValue is passed in the behavior script. This allows the developer to skip a column for editing. Previously this would only occur if EditValue was not handled.

DeleteFieldEditorAndOpenNext now skips invisible columns.

The control that DeleteFieldEditorAndOpenNext was targeting would sometimes be changed behind the scenes. This would cause CloseFieldEditor to be sent to the wrong control.

1.0.2 (build 13) ResetList code is now in dgResetList. This allows the developer to intercept

ResetList and manually call dgResetList while adding their own logic.

1.0.2 (build 14) SortDataByKey specifically uses the first line of data in the column. Previously if there were multiple lines in a value it would cause problems.

Fixed some issues in the auto scroll code used in drag/drop operations.

When setting the "scrollbar width" property the new value was not being passed into the function that sets the scrollbar width (bug 9684).

#### Maintenance

## **Noteworthy changes**

The following bug fixes are ones which may have an impact on existing code and/or may be important to a wide audience.

(changes specific to the current build are highlighted with a gray background)

#### Minor usability improvements

After observing a number of users using LiveCode for the first time, the following minor changes have been made:

- The default state of the paint tools in the tools palette is opened so they are visible on start up (existing installs are unaffected).
- The 'Hide Palettes when editing scripts' and 'Hide Message Box when editing scripts' options are now defaulted to false (existing installs are unaffected).
- On the menubar the 'Rev Online' button has been renamed 'User Samples' and a new 'Tutorials' button introduced linking directly to <a href="http://lessons.runrev.com">http://lessons.runrev.com</a>.

## Specific bug fixes (4.6.4)

(bug fixes specific to the current build are highlighted in bold)

9666 Generated test.html does not detect new LiveCode Player plugin on IE Find and replace should allow multi-line and empty replace values

## Specific bug fixes (4.6.3)

9109 Error in dictionary entries containing <, & and >

9128 URL dictionary entries don't cross reference

- Last dictionary entry preference being corrupted
- 9621 Error in dictionary entry for \$ keyword
- 9596 Typo in dicitonary entry for dispatch command

## Specific bug fixes (4.6.2)

- 9527 Application Browser lists controls in groups even if selectGroupedControls is false
- 9535 XML-RPC library still sends 'Revolution' as user-agent
- 9543 AppleScript dictionary for LiveCode present in standalones on Mac
- 9537 Error in Mobile Browser Example script

## Specific bug fixes (4.6.1)

Dictionary pane in script editor sometimes displays xmlerr.

Simulate button acts on topStack, rather than the mainStack of the topStack

Building an Android standalone in non-Commercial mode causes an error

Building a standalone with oracle causes a warning on Mac Intel

- 8975 Start center recent files can become confused
- 9470 Chrome sometimes sets global environment variables that break the message box
- 9491 Unicode text does not display which font in Text menu
- 9496 Inspector chokes with stack names containing "!"
- 9520 HTTP headers are split by word, rather than ':'

## Specific bug fixes (4.6)

Added shortcut for 'Paste Unformatted'

Mac field shortcuts do not work correctly in the Script Editor

The dictionary does not open correctly in some cases.

Pressing option in some IDE fields cause them to revert the field.

New datagrids are not created properly and can't have their Row Template's shown.

LiveTalk still present in the first pane of the preferences GUI.

Simulator menu does not filter list by available engines

- 4864 Property inspector's treatment of link style properties does not reflect reality
- 7250 'edit custom prop name' dialog resizable when it shouldn't be
- 8576 IDE processes openDoc filename incorrectly
- 8775 Continuations have an inconsistent indent in the S/E
- 9291 Body text in the about dialog is clipped initially
- 9292 Simulate button does not have a tooltip
- 9299 Substacks are unsorted in the app browser
- 9316 CFBundleVersion not set when building Mac standalones
- 9453 Dictionary note rating broken

## **Resource and Documentation Changes**

#### **User Guide**

No changes.

## **Dictionary**

A substantial number of dictionary entries have been added and updated to bring the dictionary into line with all the new features added to the mobile and server platforms. In addition to this, minor tweaks have been made to the dictionary stack in order to accommodate the new entries.

## **Mobile Examples**

The *Mobile Examples* are a collection of stacks demonstrating various features specific to the mobile platforms LiveCode supports.

These are accessible from *Help > Example Stacks and Resources* and are within the *Mobile Examples* folder.

The following changes have been made in this release:

#### Sound Example

The example queue has been updated to use the changed functionality of *iphonePlaySoundOnChannel* in *next* mode when there is no sound playing (i.e. to prepare the sound to ensure it plays with zero latency when needed).

To support this change, a *Pause* and *Resume* button have been added mapping to *iphonePauseSoundOnChannel* and *iphoneResumeSoundOnChannel*.

# **Previous Release Notes**

4.5.0 Release Notes	http://www.runrev.com/downloads/livecode/4_5_0/LiveCodeNotes-4_5_0.pdf
4.5.1 Release Notes	http://www.runrev.com/downloads/livecode/4_5_1/LiveCodeNotes-4_5_1.pdf
4.5.2 Release Notes	http://www.runrev.com/downloads/livecode/4_5_2/LiveCodeNotes-4_5_2.pdf
4.5.3 Release Notes	http://www.runrev.com/downloads/livecode/4_5_3/LiveCodeNotes-4_5_3.pdf
4.6.0 Release Notes	http://www.runrev.com/downloads/livecode/4_6_0/LiveCodeNotes-4_6_0.pdf
4.6.1 Release Notes	http://www.runrev.com/downloads/livecode/4_6_1/LiveCodeNotes-4_6_1.pdf
4.6.2 Release Notes	http://www.runrev.com/downloads/livecode/4_6_2/LiveCodeNotes-4_6_2.pdf
4.6.3 Release Notes	http://www.runrev.com/downloads/livecode/4_6_3/LiveCodeNotes-4_6_3.pdf

# Revisions

Revision 1	MW	Document created for issue with 4.6.0-dp-1.
Revision 2	MW	Updated ide bug fix list for 4.6.0-dp-2.
		Updated engine bug fix list for 4.6.0-dp-2.
		Added section on 'plain text' field properties
		Updated listStyle property section
		Updated noteworthy engine changes section
Revision 3	MW	Updated ide bug fix list for 4.6.0-dp-3
	112 77	Updated engine bug fix list for 4.6.0-dp-3
		Added section on print to pdf document outline support
Revision 4	MW	Updated ide bug fix list for 4.6.0-dp-4
110/15/07/	1,1,	Updated engine bug fix list for 4.6.0-dp-4
		Added section on 'export snapshot from with effects'
		Clarified section on print to pdf with regards to link printing
Revision 5	MW	Updated engine bug fix list for 4.6.0-dp-5
		Added section on new print link syntax
Revision 6	MW	Updated engine bug fix list for 4.6.0-dp-6
Revision 7	MW	Updated engine bug fix list for 4.6.0-dp-7
		Updated datagrid section to mention update to 1.0.2 build 12.
		Added new 'Resource and Documentation Changes' section.
Revision 8	MW	Updated engine bug fix list for 4.6.0-dp-8
		Updated noteworthy engine changes section
		Updated listStyle rtf export section
Revision 9	MW	Updated engine bug fix list for 4.6.0-rc-1
		Updated dictionary section of resource and documentation changes.
Revision 10	MW	Updated ide bug fix list for 4.6.0-rc-2
		Updated datagrid section to mention update to 1.0.2 build 13.
Revision 11	MW	
Revision 12	MW	
Revision 13	MW	No changes.
Revision 14	MW	Updated engine bug fix list for 4.6.0-gm-2

Revision 15	MW	Updated engine bug fix list for 4.6.1-dp-1
		Updated ide bug fix list for 4.6.1-dp-1
		Added details of 'initially' clause to print bookmark section.
D: 16	M	Added section of new 'revCapture' API
Revision 16	MW	Updated engine bug fix list for 4.6.1-dp-2
Revision 17	MW	Updated engine bug fix list for 4.6.1-rc-1
		Updated ide bug fix list for 4.6.1-rc-1
D · · 10	M	Added sections on Android support.
Revision 18	MW	Updated for 4.6.1-gm-1.
Revision 19	MW	Updated ide bug fix list for 4.6.1-gm-2.
Revision 20	MW	Updated engine bug fix list for 4.6.2-dp-1
D · · · 21	M	Updated ide bug fix list for 4.6.2-dp-1
Revision 21	MW	Updated engine bug fix list for 4.6.2-rc-1
D 22	1 (1)	Added section on revBrowser 'useragent' property
Revision 22	MW	Updated engine bug fix list for 4.6.2-rc-2
Revision 23	MW	No changes.
Revision 24	MM	Updated engine bug fix list for 4.6.3-dp-1
Revision 25	MM	Updated engine bug fix list for 4.6.3-dp-2
D		Added section on 'defaultNetworkInterface' property
Revision 26	MM	Updated section Resource and Documentation Changes.
Revision 27	MM	Added section on 'networkInterface' property.
<b>D</b>		Updated ide bug fix list for 4.6.3-rc-1.
Revision 28	MM	No changes.
Revision 29	MM	Updated ide bug fix list for 4.6.3-gm-2.
_		Updated engine bug fix list for 4.6.3-gm-2.
Revision 30	MM	Updated ide bug fix list for 4.6.4-dp-1.
		Updated engine bug fix list for 4.6.4-dp-1.
		Added section Shared group and background updates.
		Added section Message handling speed improvements.
Revision 31	MM	Updated engine bug fix list for 4.6.4-dp-2.
Revision 32	MM	Updated engine bug fix list for 4.6.4-dp-3.
Revision 33	MM	Updated engine bug fix list for 4.6.4-rc-1.
		Updated data grid to 1.0.2 build 14
Revision 34	MM	Updated engine bug fix list for 4.6.4-rc-2.
Revision35	MM	No changes.
Revision 36	MM	Updated engine bug fix list for 4.6.4-gm-2.
		Added section "MySQL driver updates".
Revision 37	MM	Updated engine bug fix list for 4.6.4-gm-3.